

# EDT Editor Reference Card

Order No. AV-J756A-TC

## Keypad Editing for VT52 and VT100

To use the power function on each key, press the GOLD key first and then the function key. The keypad numbers in the upper left of each key are used in DEFINE KEY operations.

## Keypad and Arrow Keys for the VT100

|    |      |      |       |
|----|------|------|-------|
| 12 | 13   | 15   | 14    |
| UP | DOWN | LEFT | RIGHT |

|                   |                   |                   |                |
|-------------------|-------------------|-------------------|----------------|
|                   | 10                | 11                | 17             |
| GOLD              | HELP              | ENDNEXT<br>PAGE   | DEFI<br>IND    |
| 7                 | 8                 | 9                 | 18             |
| BACK<br>COMMAND   | SPCL<br>FILL      | APPEND<br>REPLACE | DEL W<br>UND W |
| 4                 | 5                 | 6                 | 19             |
| ADVANCE<br>BOTTOM | BACKUP<br>TOP     | CUT<br>PASTE      | DEL C<br>UND C |
| 1                 | 2                 | 3                 | 21             |
| WORD<br>REVERSE   | END<br>DEL END    | CHAR<br>REVERSE   | ENTER<br>SUBS  |
| 0                 | LINE<br>OPEN LINE |                   |                |
|                   |                   | 16                |                |
|                   |                   | SELECT<br>RESEL   |                |

# Keypad for the VT52

|                      |                 |                 |                |
|----------------------|-----------------|-----------------|----------------|
|                      | 10              | 11              | 12             |
| END                  | HELP            | DEL<br>UNDO     | UP<br>REPLACE  |
| 7                    | 8               | 9               | 13             |
| PAGE<br>FORWARD      | REVERSE<br>PAGE | END OF<br>LINE  | DOWN<br>PAGE   |
| 4                    | 5               | 6               | 14             |
| ADVANCE<br>LEFT      | BACKSPACE       | END OF<br>FIELD | RIGHT<br>SUB   |
| 1                    | 2               | 3               | 15             |
| SPACE<br>DELETE      | END<br>OF LINE  | END<br>OF FIELD | LEFT<br>DELETE |
| 0                    | 16              | 21              |                |
| PAUSE<br>OR NUM LOCK | SELECT<br>RESET | ENTER<br>SUB    |                |

## Keyboard Functions

|                     |                                                                |
|---------------------|----------------------------------------------------------------|
| BACKSPACE           | Moves the cursor to the beginning of a line                    |
| DELETE              | Erases the character to the left of the cursor                 |
| GOLD <i>integer</i> | Repeats any keypad function except SPECINS, DELETE, and CTRL/U |
| LINE FEED           | Erases the word to the left of the cursor                      |
| CTRL/A              | Computes tab level                                             |
| CTRL/C              | Ends the current operation and returns EDT to keypad editing   |
| CTRL/D              | Decreases tab level                                            |
| CTRL/E              | Increases tab level                                            |
| CTRL/K              | Defines key                                                    |
| CTRL/T              | Adjusts tabs                                                   |
| CTRL/U              | Deletes to start of line                                       |
| CTRL/W              | Refreshes screen                                               |
| CTRL/Z              | Returns to the editing prompt                                  |

## Starting EDT

Depending on your system, you will use one of the following command lines:

**DCL/PDS:** `ED - EDT <file name>ED`

**MCR/CCL:** `ED - EDT <file name>ED`

To begin keypad editing, enter the CHANGE command after the asterisk.

## Ending the Editing Session

To end the session and save your edits to a file, press the GOLD and COMMAND function keys and enter the EXIT command. To end the session without saving your edits, enter QUIT instead of EXIT.

## Getting Help

Pressing the **HELP** key in keypad editing provides a diagram of keypad functions, as well as explanations of some common keyboard functions. When you then press a keypad key, a description of the functions of that key appears on the screen.

## Using the GOLD Function

**GOLD** Specifies the lower function of the two functions named on a keypad key. Also repeats a function and allows special character insertion.

**RESET** Cancels a GOLD function or a select range.

## Entering Commands

**COMMAND** Displays the **COMMAND:** prompt when you press the **GOLD** and **COMMAND** function keys, then lets you enter a command.

**ENTER** Lets you complete the command.

## Using Arrow Functions



Moves the cursor to the next character.



Moves the cursor one character below.



Moves the cursor to the preceding character.



Moves the cursor to the character above.

## Changing Directional Mode

**ADVANCE** Changes the direction of cursor movement to the right and downward.

**BACKUP** Changes the direction of cursor movement to the left and upward.

## **Moving the Cursor by Standard Units of Text**

|         |                                                      |
|---------|------------------------------------------------------|
| BOTTOM  | Moves the cursor directly to the end of the buffer.  |
| TOP     | Moves the cursor directly to the top of the buffer.  |
| LINE    | Moves the cursor to the beginning of a line.         |
| CHAR    | Moves the cursor to the next or preceding character. |
| EOL     | Moves the cursor to a line terminator character.     |
| WORD    | Moves the cursor to the beginning of a word.         |
| PAGE    | Moves the cursor to the top of a page.               |
| SECTION | Moves the cursor to the top of a section.            |

## **Searching for Strings in the File**

|          |                                                                                                    |
|----------|----------------------------------------------------------------------------------------------------|
| FIND     | Type a search string and then press the ADVANCE key or BACKUP key to specify the search direction. |
| FINDNEXT | Searches for another occurrence of a word or phrase that matches the latest search string.         |

## **Repeating Functions**

If the VT100 autorepeat feature is enabled, you can repeat a single key function and single character insertion by holding the key down. For the same effect on a VT52, hold down both a function key and the REPEAT key.

|                     |                                                                 |
|---------------------|-----------------------------------------------------------------|
| GOLD <i>Integer</i> | Repeats any keypad function except SPECINS, DELETE, and CTRL/U. |
|---------------------|-----------------------------------------------------------------|

*(Continued)*

# EDT Keypad Editing

## Tear-off Card

To use the lower function on each key, press the GOLD key first and then the function key. The keypad numbers in the upper left of each key are used in DEFINE KEY operations.

### Keypad and Arrow Keys for the VT100

|          |            |            |             |
|----------|------------|------------|-------------|
| 12<br>UP | 13<br>DOWN | 15<br>LEFT | 14<br>RIGHT |
|----------|------------|------------|-------------|

|                        |                          |                        |                      |
|------------------------|--------------------------|------------------------|----------------------|
| GOLD                   | 10<br>HELP               | 11<br>ENDNEXT<br>END   | 17<br>DEL L<br>UND L |
| 7<br>PAGE<br>COMMAND   | 8<br>REF<br>FILL         | 9<br>APPLND<br>REPLACE | 18<br>DEL W<br>UND W |
| 4<br>ADVANCE<br>BOTTOM | 5<br>BACKUP<br>TOP       | 6<br>CUT<br>PASTE      | 19<br>DEL C<br>UND C |
| 1<br>WORD<br>COMMAND   | 2<br>FILL<br>DEL FILL    | 3<br>CHAR<br>SPECIFY   | 21<br>ENTER<br>SUBE  |
| 0<br>LINE<br>OPEN LINE | 16<br>SEL FILL<br>REPEAT |                        |                      |

# EDT Keypad Editing

## Tear-off Card

To use the lower function on each key, press the GOLD key first and then the function key. The keypad numbers in the upper left of each key are used in DEFINE KEY operations.

### Keypad for the VT52

|                   |                |                |                |
|-------------------|----------------|----------------|----------------|
|                   | 10             | 11             | 12             |
| GOLD              | HELP           | HI L<br>LAST   | UP<br>REPLACE  |
| 7                 | 8              | 9              | 13             |
| PAGE<br>COMMAND   | FNDNXT<br>FIND | HL W<br>UND W  | DOWN<br>SPCL   |
| 4                 | 5              | 6              | 14             |
| ADVANCE<br>LEFT   | BACKUP<br>TOP  | DEL C<br>END C | RIGHT<br>SPCL  |
| 1                 | 2              | 3              | 15             |
| WORD<br>CHANGE    | EOL<br>DEL EOL | OUT<br>PASTE   | LEFT<br>APPEND |
| 0                 |                | 16             | 21             |
| LINE<br>OPEN LINE |                | SPCL<br>DEF    | ENTER<br>SUBS  |

## **Inserting Material into the Main Buffer**

To insert any printing characters on the keyboard, type the characters. To insert nonprinting characters, use the SPECINS functions.

|           |                                                                                                                                                                                                   |
|-----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| SPECINS   | Inserts nonprinting characters. Press the GOLD key, type the ASCII decimal equivalent of the nonprinting character you want to insert, and then use the SPECINS function to insert the character. |
| OPEN LINE | Inserts a new line terminator at the cursor's right.                                                                                                                                              |

## **Selecting a Range of Text**

|        |                                                                                                                                                                                                                                                                                      |
|--------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| SELECT | Marks the start of a select range. When you move the cursor, use the following functions and commands at the end of the select range:<br><br>Functions: APPEND, CHNGCASE, CUT, FILL, REPLACE<br><br>Commands: FILL, TABS, ADJUST<br><br>The RESET function cancels the select range. |
|--------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

## **Moving, Copying and Reformatting Text**

|        |                                                                        |
|--------|------------------------------------------------------------------------|
| APPEND | Deletes the select range and stores it at the end of the paste buffer. |
| CUT    | Deletes the select range and stores it in the paste buffer.            |
| FILL   | Reformats the text lines in the select range.                          |
| PASTE  | Inserts the string from the paste buffer.                              |

## **Deleting and Restoring by Standard Units of Text**

|           |                                                                                                                |
|-----------|----------------------------------------------------------------------------------------------------------------|
| CTRL/U    | Deletes to the preceding line terminator and stores the string in the line buffer.                             |
| DEL C     | Deletes the cursor's current character and stores it in the character buffer.                                  |
| DEL EOL   | Deletes to the next line terminator and stores the string in the line buffer.                                  |
| DELETE    | Deletes the preceding character and stores it in the character buffer.                                         |
| DEL L     | Deletes through the next line terminator and stores the string in the line buffer.                             |
| DEL W     | Deletes to the first character of the next word and stores the string in the word buffer.                      |
| LINE FEED | Deletes through the first character of the current or preceding word and stores the string in the word buffer. |
| UND C     | Inserts the character from the character buffer.                                                               |
| UND L     | Inserts the string from the line buffer.                                                                       |
| UND W     | Inserts the string from the word buffer.                                                                       |

## **Substituting**

|                   |                                                                                                     |
|-------------------|-----------------------------------------------------------------------------------------------------|
| <b>CHNGCASE</b>   | Changes the case of the characters in a selected range.                                             |
| <b>REPLACE</b>    | Replaces the characters in a select range with the characters in the paste buffer.                  |
| <b>SUBSTITUTE</b> | When the cursor is at a search string, completes the REPLACE function and then the FNCNXT function. |